

SigMT - User Manual

v. 1.1

K.S. Ajithabh

September 30, 2023

Introduction

SigMT is a python package designed for the processing of the raw magnetotelluric (MT) data to obtain the MT impedance and tipper estimates. It works in an automated way, so that manual time series inspection and editing are not required. Mahalanobis based data selection tool is implemented in the package to avoid the manual editing of time series. The final impedance estimation is done using the robust estimation method. Different data selection tools such as coherency threshold, polarization direction are included in this package. This document is a guide to use the SigMT package. At present, only ‘.ats’ file formats from ADU07 (Metronix Geophysics) is supported.

Contents

1	Supported file formats	3
2	Getting started	3
3	Overview of the package	4
4	Setting of parameters	7
5	An example	7
5.1	Running the program	7
5.2	Creating EDI file	10
5.3	Data selection tools	15
5.4	Remote reference	18

1 Supported file formats

- *.ats file format from ADU-07 by Metronix Geophysics

2 Getting started

The program is written as a project in Spyder IDE with the support of ‘Anaconda’ Python Distribution. I suggest installation of the Anaconda first to start with this package. You can download the latest version of Anaconda for Windows/Linux/Mac from Anaconda website (<https://www.anaconda.com/>). Anaconda provides all necessary python modules for the scientific computations.




Figure 1: Anaconda Navigator

After installation of Anaconda, you can check in Anaconda Navigator (Figure 1) whether Spyder is installed or not. If not installed by default, please install Spyder using install button in Anaconda Navigator.

Once Anaconda and Spyder is ready, you can download the SigMT package as zip from GitHub (Figure 2). Extract the compressed folder to your local drive. Then open ‘Spyder IDE’, select Projects and click ‘Open Project’ (Figure 3).




Figure 2: Download the package




Figure 3: Open Project in Spyder

Navigate to extracted SigMT project folder and select it. Now you are in SigMT package and all set to start processing your MT data!!

3 Overview of the package

The file ‘main_script.py’ is the file you need to run the package for single site processing. But, if you need to carry out Remote reference, please use ‘main_script_RR.py’ file.

The files such as mtproc.py, mtprocRR.py, var.py, mahaDist.py, data_sel.py, tipper.py are written to perform different tasks in package and need not to be edited.

I suggest editing of main_script.py, main_script_RR.py and config.py as per your needs. The more description of these files are given below.

First of all, create a project folder and copy all your MT sites in it (as in Figure 4).




Figure 4: Project folder

The measurements should be in the site folder as in Figure 5. There should not be any other extra folders inside the site folder.




Figure 5: Site folder

There are three places, code can be modified in ‘main_script.py’ and ‘main_script_RR.py’ files to provide site folder path, decimation and data selection constraints.

First edit is required to provide the sites folder path. Copy the location of folder where sites are kept and copy to the variable ‘project_path’ as in Figure 6.

```

D:\Pyth\demo - Spyder (Python 3.9)
File Edit Search Source Run Debug Consoles Projects Tools View Help
D:\Pyth\demo\main_script.py
main_script.py
1  # -*- coding: utf-8 -*-
2  """
3      Created on Mon May  4 16:49:35 2020
4
5      @author: AJITHABH
6  """
7  import mtproc, coh, coherence, tipper, mahaDist
8  from scipy import signal
9  from matplotlib import pyplot as plt
10 import numpy as np
11 import os
12 import time
13 import math
14 #
15 #
16 # provide project path where sites are kept
17 project_path = 'D:/NGRI/FIELD RAW DATA/demo/' (highlighted)
18 #
19 s.chdir(project_path)
20 sites = [d for d in os.listdir('..') if os.path.isdir(d)]
21 # all site names are stored in variable sites
22 print('Sites in the project are: ')
23 print(sites)
24 selectedsite = input("Enter the site: ")
25 siteindex = sites.index(selectedsite)
26 measid = mtproc.measid(siteindex)
27 del siteindex
28 os.chdir(project_path[selectedsite])
29 all_meas = [d for d in os.listdir('..') if os.path.isdir(d)]
30 for i in range(len(all_meas)):
31     print(all_meas[i])

```

Figure 6: Give project path (sites folder)

Second edit is required in case you require decimation. The highlighted portions in Figure 7 is written to perform decimation. Keep ‘dflag’ 1 if you need to used decimation, else always keep 0. Suppose you need to decimate the data sampled at 32 Hz. If you use [8,4], then the data will be first decimated to $32/8 = 4$ Hz, then $4/4 = 1$ Hz. So, the output will be 1 Hz. Direct decimation using [32] is not recommended. If you used [8,8,4], the data will be decimated to 0.125 Hz. Similarly, you can decimate to any sampling frequencies.

```

D:\Pyth\SigMT-Distribution - Spyder (Python 3.9)
File Edit Search Source Run Debug Consoles Projects Tools View Help
D:\Pyth\SigMT-Distribution\main_script.py
main_script.py
43 #
44 # ===== Selection of site and setting a path =====
45 sites, selectedsite, measid, all_meas, select_meas, proc_path = mtproc.makeprocpath(project_pat
46 #
47 # ===== Site is selected and path is created =====
48 #
49 # ===== Time series reading starts =====
50 procinfo = {}
51 ts, procinfo['fs'], procinfo['sensor_no'], timeline, procinfo['ChoppStat'], loc = mtproc.ts(pro
52 #===== Decimation section =====
53 # Keep dflag = 0 if decimation is not required
54 dflag = 0
55 if dflag == 1:
56     decimate = [8,8,4]
57     for d in decimate:
58         ts['tsEx'] = signal.decimate(ts.get('tsEx'), d, n=None, ftype='fir')
59         ts['tsEy'] = signal.decimate(ts.get('tsEy'), d, n=None, ftype='fir')
60         ts['tsHz'] = signal.decimate(ts.get('tsHz'), d, n=None, ftype='fir')
61         ts['tsHy'] = signal.decimate(ts.get('tsHy'), d, n=None, ftype='fir')
62         ts['tsNx'] = signal.decimate(ts.get('tsNx'), d, n=None, ftype='fir')
63         ts['tsNy'] = signal.decimate(ts.get('tsNy'), d, n=None, ftype='fir')
64         procinfo['fs'] = procinfo.get('fs')/d
65 #===== Decimation section end =====
66 #
67 # Some calculations and printing some information
68 # No need to edit
69 procinfo['nofs'] = len(ts['tsEx'])
70 procinfo['notch'] = 0 # Notch flag 1 - On, 0 - Off
71 print('-----')
72 print('Site: ' + selectedsite)
73 print('Measurement directory: ' + all_meas[select_meas])
74 print('fs: ' + str(procinfo.get('fs')) + ' Hz')
75 print('no. of measurement numbers: ' + str(procinfo['nofs']))

```

Figure 7: Decimation

Third edit is required to control data selection tools. The highlighted portions in Figure 8 is written to perform data selection. Coherency threshold and polarization direction based selections are included in the package. More detailed description is given in section 5.3.

```

=====Data selection tools section. Coherency threshold & Polarization direction
# Calculation of coherency values for all time windows
AllcohEx = data_sel.cohEx(bandavg)
AllcohEy = data_sel.cohEy(bandavg)
# Calculation of polarization directions for all time windows
alpha_degH,alpha_degE = data_sel.pdvalues(bandavg)
#
===== Coherency threshold =====
ctflag = 0 # Give '1' to perform coherency threshold based selection
minpercent = 20 # Minimum percentage of windows required
CohThre = 0.9 # Coherency Threshold value Range: (0,1)
[cohMatrixEx, cohMatrixEy] = data_sel.performct(ctflag,CohThre,minpercent,ftlist,bandavg,AllcohEx,AllcohEy)
#
===== Polarization direction =====
pdflag = 0 # Give '1' to perform polarization direction based selection
pdlim = [-10,10] # Ploarization direction limit
alpha = alpha_degE # Use either alpha_degE (electric field) or alpha_degH (magnetic field)
pdmat = data_sel.performpd(pdflag,pdlim,alpha,bandavg)

# This can be used to mask time windows based on the polarization directions
mwflag = 0 # Give '1' to perform mask windows
timewindow_limits = [0,40] #Time window limits
mwmat = data_sel.performmw(mwflag,timewindow_limits,bandavg)

=====End of data selection tools section

```

Figure 8: Data selection tools section

4 Setting of parameters




Figure 9: Configuration file

The user can define parameters such as FFT length, parzen radius, mahalanobis distance for impedance calculation, mahalanobis distance for tipper calculation. The configuration file is shown in the Figure 9. Keep FFT_Length and parzen_radius as 0 to choose default values. Or else, provide values as per the need.

5 An example

5.1 Running the program

I am showing an example of processing here. Give the sites folder path in ‘main_script.py’ file and run the code as in the Figure 10

```

D:\Pyth\demo - Spyder (Python 3.9)
File Edit Search Source Run Debug Consoles Projects Tools View Help
D:\Pyth\demo
demo
  -> callfiles
    coh.py
    coherence.py
    mahaDist.py
    main_script.py
    main_script_I
    MPD.py
    mproc.py
    mprocRR.py
    mprocRRR.py
    plotData.py
    plotMD.py
    plotMPD.py
    tipper.py
    tipperR.py
    write2dI_da
    write2dI_he
    write2dI_co
    write2dI_py

```

Run

```

main_script.py X Run
1  # -*- coding: utf-8 -*-
2  """
3  Created on Mon May  4 16:49:35 2020
4
5  @author: AJITHABH
6  """
7  import mproc, coh, coherence, tipper, mahaDist
8  from scipy import signal
9  from matplotlib import pyplot as plt
10 import numpy as np
11 import os
12 import time
13 import math
14 #
15 #
16 # provide project path where sites are kept
17 project_path = 'D:/NGRI/FIELD RAW DATA/demo/' #<----- Line selected
18
19 os.chdir(project_path)
20 sites = [d for d in os.listdir('.') if os.path.isdir(d)]
21 # all site names are stored in variable sites
22 print('Sites in the project are: ')
23 print(sites)
24 # user site = input("Enter the site: ")
25 selectedsite = 'KL33A'
26 siteindex = sites.index(selectedsite)
27 measid = mproc.measid(siteindex)
28 del siteindex
29 os.chdir(project_path+selectedsite)
30 all_meas = [d for d in os.listdir('.') if os.path.isdir(d)]
31
32 for i in range(len(all_meas)):
33     ...

```

Source | Console | Object

Usage

Here you can get help of any object by pressing **Ctrl+H** in front of it, either on the Editor or the Console.

Help can also be shown automatically after writing a left parenthesis next to an object name to activate this behavior in **Preferences > Help**.

New to Spyder? Read our [tutorial](#)

Console 1/A X

Python 3.9.7 (default, Sep 16 2021, 16:59:28) [MSC v.1916 64 bit (AMD64)]
Type "copyright", "credits" or "license" for more information.
IPython 7.29.0 -- An enhanced Interactive Python.
In [1]:

LSP Python: ready cond: base (Python 3.9.7) Line 147, Col 1 UTF-8 CRLF RW Mem 52%

Figure 10: Give path and run the program

Once we run the program, the names of all sites will be displayed in the console (Figure 11). Then enter the site name to be processed and click ‘Enter’.

```

D:\Pyth\demo - Spyder (Python 3.9)
File Edit Search Source Run Debug Consoles Projects Tools View Help
D:\Pyth\demo
demo
  -> callfiles
    coh.py
    coherence.py
    mahaDist.py
    main_script.py
    main_script_I
    MPD.py
    mproc.py
    mprocRR.py
    mprocRRR.py
    plotData.py
    plotMD.py
    plotMPD.py
    tipper.py
    tipperR.py
    write2dI_da
    write2dI_he
    write2dI_co
    write2dI_py

```

Run

```

main_script.py X Run
1  # -*- coding: utf-8 -*-
2  """
3  Created on Mon May  4 16:49:35 2020
4
5  @author: AJITHABH
6  """
7  import mproc, coh, coherence, tipper, mahaDist
8  from scipy import signal
9  from matplotlib import pyplot as plt
10 import numpy as np
11 import os
12 import time
13 import math
14 #
15 #
16 # provide project path where sites are kept
17 project_path = 'D:/NGRI/FIELD RAW DATA/demo/' #<----- Line selected
18
19 os.chdir(project_path)
20 sites = [d for d in os.listdir('.') if os.path.isdir(d)]
21 # all site names are stored in variable sites
22 print('Sites in the project are: ')
23 print(sites)
24 # user site = input("Enter the site: ")
25 selectedsite = 'KL33A'
26 siteindex = sites.index(selectedsite)
27 measid = mproc.measid(siteindex)
28 del siteindex
29 os.chdir(project_path+selectedsite)
30 all_meas = [d for d in os.listdir('.') if os.path.isdir(d)]
31
32 for i in range(len(all_meas)):
33     ...

```

Source | Console | Object

Usage

Here you can get help of any object by pressing **Ctrl+H** in front of it, either on the Editor or the Console.

Help can also be shown automatically after writing a left parenthesis next to an object name to activate this behavior in **Preferences > Help**.

New to Spyder? Read our [tutorial](#)

Console 1/A X

Python 3.9.7 (default, Sep 16 2021, 16:59:28) [MSC v.1916 64 bit (AMD64)]
Type "copyright", "credits" or "license" for more information.
IPython 7.29.0 -- An enhanced Interactive Python.
In [1]: runfile('D:/Pyth/demo/main_script.py', wdir='D:/Pyth/demo')
Sites in the project are:
['KL33A', 'LU16', 'LU33A']
Enter the site: KL33A

LSP Python: ready cond: base (Python 3.9.7) Line 36, Col 31 UTF-8 CRLF RW Mem 56%

Figure 11: Enter the site name from the list

Then all measurements in the selected site will be displayed. Give the measurement number as input. For example, I selected number 16 for the processing in Figure 12.

The screenshot shows the Spyder Python IDE interface. On the left, the file tree displays a 'demo' folder containing various Python scripts like coh.py, coherence.py, mahaDist.py, etc. The main script, 'main_script.py', is open in the editor. In the bottom right corner, there is a 'Console 2/A' window. A red box highlights the command 'Select measurement: 16' and the list of available measurements:

```

Sites in the project are:
['KL33A', 'LU16', 'LU33A']

Enter the site: KL33A
[[0, 'meas_2019-08-29_09-01-00'],
 [1, 'meas_2019-08-29_09-04-00'],
 [2, 'meas_2019-08-29_09-11-00'],
 [3, 'meas_2019-08-29_09-18-00'],
 [4, 'meas_2019-08-29_09-25-00'],
 [5, 'meas_2019-08-29_14-06-00'],
 [6, 'meas_2019-08-29_14-13-00'],
 [7, 'meas_2019-08-29_14-36-00'],
 [8, 'meas_2019-08-29_14-59-00'],
 [9, 'meas_2019-08-29_15-01-00'],
 [10, 'meas_2019-08-29_15-23-00'],
 [11, 'meas_2019-08-29_16-05-00'],
 [12, 'meas_2019-08-29_16-28-00'],
 [13, 'meas_2019-08-29_16-49-00'],
 [14, 'meas_2019-08-29_16-52-00'],
 [15, 'meas_2019-08-29_21-54-00'],
 [16, 'meas_2019-08-29_21-57-00'],
 [17, 'meas_2019-08-29_22-19-00']]
Select measurement: 16

```

Figure 12: Enter the measurement number

Then some details about the measurement such as sampling frequency, coil numbers, length of time series, window length, and number of windows will be displayed (Figure 13). Then the processing will be started.

The screenshot shows the Spyder Python IDE interface. The 'Basic details' section is highlighted in red. A red arrow points from the 'Progress' section to the 'Console 2/A' window, which displays the processing output:

```

NT site: KL33A
Measurement directory: meas_2019-08-29_21-57-00
fs=4096.0 Hz
Sensor numbers:
{'Hx': [300], 'Hy': [301], 'Hz': [302]}
Length of time series = 4915200
-----
Unused variables deleted.
-----
Window Length selected: 16384
Time series overlap: 50%
No. of stacks: 599
-----
Band averaging over target frequencies:
35|| , 17.599 [08:09:05;13, 1.867/s]

```

Figure 13: Processing..

After completing the processing, figure showing apparent resistivity and phase curves, coherency values and tipper data will be plotted and can be seen in 'Plots' section (Figure 14).




Figure 14: Output figures

5.2 Creating EDI file

The data is processed band wise. After completing processing for all measurements, the data should be joined to create the EDI files. One site may have many measurements. So, we have to save data in text files.

Create a folder anywhere. For example, a folder named ‘Outputs’ (as in Figure 15). Inside that folder, make a folder with site name. Create a folder named ‘bands’ inside site folder (Figure 15).




Figure 15: Create a folder to save processed data

Now come to Spyder and open ‘write2file.py’ script. Give the path to bands folder in

the variable ‘f’. Give sampling frequency as file name. For example ‘4096Hz.txt’. Select all script lines using ‘Ctrl+A’ and right click. Select ‘Run section or current line’ (Figure 16).




Figure 16: Save data in file

Now save header information to a file in site output folder. It is required for EDI file creation. Open ‘write2edi-header.py’ file and give path to sites folder (output) in variable ‘f’. Select all lines, right click and select ‘Run section or current line’ (Figure 17)




Figure 17: Save header information

After executing processing for a measurement, always close ‘Console’ (Figure 18).

The screenshot shows the Spyder Python IDE interface. On the left, there's a file tree for a 'demo' folder containing various Python scripts like 'coh.py', 'coherence.py', 'mahaDist.py', etc. In the center-left, two code editors are open: 'main_script.py' and 'write2file.py'. The code in 'main_script.py' includes imports for numpy, pandas, and procinfo, along with logic for calculating latitudes and longitudes from a location object. It also includes code for writing to a file named 'all.txt'. The code in 'write2file.py' is mostly blank. On the right side, there's a plot window titled 'KL33A - meas_2019-08-29_21-57-00 (4096.0 Hz)' showing a log-log plot of data. Below the plot is a 'Console 2/A' window with some command-line output.

Figure 18: Close console after processing a measurement

Similarly, I processed for 1024 Hz measurement and save data in bands folder of KL33A. Now the measurement data can be seen in the folder (Figure 19). Create a text file named 'all.txt'.




Figure 19: Create a file all.txt

Copy the data from 4096Hz.txt file and 1024Hz.txt file to all.txt as in Figure 20. Always keep higher frequency data in the top.

The screenshot shows a Notepad window with several lines of numerical data. A red box highlights the first two lines of data. The data consists of approximately 20 columns of floating-point numbers.

```

7.656775755E+02 -5.011017299E+01 -4.154310406E+01 7.690974966E+02 7.137734152E+02 -1.587754292E+03 -1.218250757E+03 7.85046
5.710385405E+02 -7.023137803E+01 4.546872036E+01 7.53212658E+02 5.796599233E+02 -1.415793899E+03 -1.176317884E+03 2.60640
4.258777131E+02 1.020347167E+01 4.391553914E+01 5.871055244E+02 5.437691556E+02 -1.148521956E+03 -9.583387031E+02 4.13674
3.176174875E+02 1.315706979E+01 3.155075649E+01 5.034976345E+02 4.759532461E+02 -1.012805535E+03 -8.473847069E+02 1.1033
2.368775478E+02 1.655562791E+01 -2.333572712E+01 4.343104281E+02 4.131497498E+02 -8.837328385E+02 -7.499882991E+02 -7.3938
1.766210846E+02 1.180344260E+01 1.706784536E+01 3.730951850E+02 3.616474242E+02 -7.687551942E+02 -6.66555193E+02 2.6823
1.823610332E+02 2.023137805E+01 3.200077750E+01 3.200077750E+01 3.200077750E+01 -5.357423644E+02 -5.357423644E+02 -2.1656
9.826127078E+01 1.784090015E+01 8.591398491E+00 2.869321752E+02 2.772102045E+02 -5.782378358E+02 -5.386274967E+02 -2.5353
7.328276869E+01 2.158549529E+01 -1.540289672E+00 2.339886403E+02 2.392160219E+02 -4.929963171E+02 -4.656261398E+02 -3.9715
5.465392565E+01 2.051765238E+01 3.665197224E+00 1.988979153E+02 2.062920146E+02 -4.215247974E+02 -4.0911349518E+02 -4.225558486E
4.076062685E+01 1.725275253E+01 8.632947485E+00 1.689954099E+02 1.761413590E+02 -3.592160173E+02 -3.542342353E+02 -3.963645538E
3.839987346E+01 1.161852426E+01 1.189268797E+01 1.422661705E+02 1.490621252E+02 -3.076347905E+02 -3.094971547E+02 -3.399758912E
2.267147831E+01 5.388805539E+00 1.212027081E+01 1.222749664E+02 1.239583939E+02 -2.623526812E+02 -2.688048867E+02 -2.247227507E
1.698827615E+01 -4.158872013E-01 8.224226839E+00 1.074974781E+01 1.000935457E+02 -2.248245866E+02 -2.311040449E+02 -9.821699209E
1.261018854E+00 -2.430117759E+00 2.941252935E+00 9.858238249E+01 8.209989388E+01 -1.923449684E+02 -2.045860126E+02 -2.628248635E
9.045592158E+00 -2.80500916E+00 3.191926855E+00 9.106293307E+01 6.923849138E+01 -1.626259582E+02 -1.756825620E+02 9.44092
7.013871582E+00 -1.072436996E-02 6.234486558E+00 8.521943830E+01 6.108917137E+01 -1.484895319E+02 -1.536555487E+02 1.11451
7.230910660E+00 5.565941568E+00 -5.320871341E+00 7.417234872E+01 4.881990602E+01 -1.127249942E+02 -1.31398712E+02 4.99375

```

Figure 20: Copy data to all.txt file

Now, again go to Spyder and open ‘write2edi-data.py’ file. Give file path to ‘all.txt’ and path of sites folder in variables ‘edifilename’ and ‘f’ (Figure 21).

The screenshot shows the Spyder IDE interface with the ‘write2edi-data.py’ script open. The code reads data from ‘all.txt’, processes it, and writes it to an EDI file. A context menu is open over the code editor, with the option ‘I. Insert selection or current line F9’ highlighted.

```

# -*- coding: utf-8 -*-
"""
Created on Wed Jan 13 15:47:38 2021
@author: AJITHABH
"""

import pandas as pd
import numpy as np

edifilename = 'C:/Users/Ajithabh/Desktop/Outputs/KL33A/bands/LL.EDI'
f = open('C:/Users/Ajithabh/Desktop/Outputs/KL33A/KL33A-04TA.EDI', 'w')

data = pd.read_csv(edifilename, sep='\t', lineterminator='\n')
data = np.asarray(data)
freq = data[:,0]
zxx = data[:,1]
zxy = data[:,2]
zxyr = data[:,3]
zxyt = data[:,4]
zyx = data[:,5]
zyxr = data[:,6]
zyxt = data[:,7]
zyxy = data[:,8]
zxyvar = data[:,9]
zxyvar = data[:,10]
zyxvar = data[:,11]
zyyvar = data[:,12]
Tyr = data[:,13]
TxR = data[:,14]
TxT = data[:,15]
Tyr = data[:,15]
TyI = data[:,16]

```

Figure 21: Write data as in EDI

Now, two files are existing in sites folder (Figure 22). Copy data in the file KL33A- DATA.edi to the end of header information in KL33A-HEADER.edi file (Figure 23). Please correct ‘NFREQ’ variable with actual number of frequencies in the data (Figure 23). Now, KL33A-HEADER.edi is a standard EDI file ready to use.




Figure 22: Files ready to create EDI

```
*KL33A-HEADER.edi - Notepad
File Edit View
>HMEAS ID=4.001 CHTYPE=HY X=0.00000000E+00
Y=0.00000000E+00 Z=0.00000000E+00
ACQCHAN="ADU07/MFS06 /0/" GAIN=1 MEASDATE=08/29/2019
AZH=9.00000000E+01 DIP=0.00000000E+00
SENSOR=MFS06 /
>HMEAS ID=5.001 CHTYPE=HZ X=0.00000000E+00
Y=0.00000000E+00 Z=0.00000000E+00
ACQCHAN="ADU07/MFS06 /0/" GAIN=1 MEASDATE=08/29/2019
AZH=0.00000000E+00 DIP=0.00000000E+00
SENSOR=MFS06 /
>=HTSCT
>SECTID=KL33A
NFREQ=13
HX=3.001
HY=4.001
HZ=5.001
EX=1.001
EY=2.001
>FREQ //17
5.7103854095E+02 4.258777131E+02 3.176174875E+02 2.368775478E+02 1.766621010E+02
5.317537193E+02 9.826127078E+01 3.28275869E+01 5.465392565E+01 4.076062685E+01
3.039907346E+01 2.267147831E+01 1.698827615E+01 1.261810854E+01 9.404556446E+00
7.013871582E+00 5.230910660E+00
>ZXXR //17
-7.023137803E+01 1.020347167E+01 1.315706979E+01 1.655562791E+01 1.870547240E+01
2.023157685E+01 1.7840000015E+01 2.158549529E+01 2.051765238E+01 1.725275253E+01
1.361852426E+01 5.388805539E+00 -4.158872013E-01 -2.430117559E+00 -2.661894916E+00
-1.072436996E-02 5.565941568E+00
Ln 58, Col 11
100% Windows (CRLF) UTF-8
```

Figure 23: Edit NFREQ and save EDI

5.3 Data selection tools

```
=====Data selection tools section. Coherency threshold & Polarization direction
# Calculation of coherency values for all time windows
AllcohEx = data_sel.cohEx(bandavg)
AllcohEy = data_sel.cohEy(bandavg)
# Calculation of polarization directions for all time windows
alpha_degH,alpha_degE = data_sel.pdvalues(bandavg)
#
===== Coherency threshold =====
ctflag = 0 # Give '1' to perform coherency threshold based selection
minpercent = 20 # Minimum percentage of windows required
CohThre = 0.9 # Coherency Threshold value Range: (0,1)
[cohMatrixEx, cohMatrixEy] = data_sel.performct(ctflag,CohThre,minpercent,ftlist,bandavg,AllcohEx,AllcohEy)
#
===== Polarization direction =====
pdflag = 0 # Give '1' to perform polarization direction based selection
pdlim = [-10,10] #Polarization direction limit
alpha = alpha_degE # Use either alpha_degE (electric field) or alpha_degH (magnetic field)
pdmat = data_sel.performpd(pdflag,pdlim,alpha,bandavg)

# This can be used to mask time windows based on the polarization directions
mwflag = 0 # Give '1' to perform mask windows
timewindow_limits = [0,40] #Time window limits
mwmat = data_sel.performmw(mwflag,timewindow_limits,bandavg)

=====End of data selection tools section
```

Figure 24: Data selection tools section

In Figure 24, we can see the data selection tools part of package. If `ctflag` is 1, the coherency threshold will be activated. The coherency threshold value can be provide in ‘`CohThre`’ variable. You can see the coherency values for each target frequency using the ‘`plot-coherency.py`’ script. Give `Z_all = bandavg.get('Zxy_single')` to see coherency of xy component and `Z_all = bandavg.get('Zyx_single')` for yx component. Once you run the script, coherency plots will be displayed for each target frequency as in Figure 26. By analysing the values in the figure, you can set a coherency threshold value. In this latest update of the SigMT, we have added the adaptive coherency threshold selection. That means, you have to define at least how much data should left after applying coherency threshold. So, you have to give the minimum percentage of data required in the variable ‘`minpercent`’.

I will explain how it works. Let’s consider a dataset comprising 100 time windows. Among these, only 10 exhibit a coherency value greater than 0.9. So, if we set ‘`CohThre=0.9`’ and ‘`minpercent=20`’, the program will autonomously decrement the ‘`CohThre`’ value by 0.01 until reaches a threshold where at least 20 time windows having that ‘`CohThre`’ value. In essence, this ensures that 20% (‘`minpercent`’) of the total data is available, preventing the program from terminating due to an insufficient number of time windows for subsequent computations.

The screenshot shows the Spyder Python IDE interface. The left sidebar displays a file tree with a 'demo' folder containing various Python files like 'coh.py', 'coherency.py', 'mahaDist.py', etc. The main editor window shows the content of 'plotcoherency.py'. A context menu is open over the line of code 'blue': (0.0, 0.0, 0.0), with the 'Go to definition' option highlighted. The status bar at the bottom right indicates 'ipython console History RW Mem 68%'. On the right, there's a 'Source Editor Object' tab bar, a '0' count for the 'Console 1/A' tab, and a 'Warning' message about inline plots.

```
1 #!/usr/bin/python
2 # -*- coding: utf-8 -*-
3 # Thu Aug 20 15:52:42 2020
4 #
5 # AJITHABH
6 #
7
8 import matplotlib.pyplot as plt
9 plt.use('TKAgg')
10 from matplotlib import colors
11 red = ((0.0, 0.0, 0.0),
12        (0.1, 0.5, 0.5),
13        (0.2, 0.0, 0.0),
14        (0.4, 0.2, 0.2),
15        (0.6, 0.0, 0.0),
16        (0.8, 1.0, 1.0),
17        (1.0, 0.0, 0.0))
18 green = ((0.0, 0.0, 0.0),
19           (0.1, 0.0, 0.0),
20           (0.2, 0.0, 0.0),
21           (0.4, 1.0, 1.0),
22           (0.6, 1.0, 1.0),
23           (0.8, 0.0, 0.0),
24           (1.0, 0.0, 0.0))
25 blue = ((0.0, 0.0, 0.0),
26          (0.1, 0.5, 0.5),
27          (0.2, 1.0, 1.0),
28          (0.4, 1.0, 1.0),
29          (0.6, 0.0, 0.0),
30          (0.8, 0.0, 0.0),
31          (1.0, 0.0, 0.0))
32
33 plt.register_cmap(name='LinearS', colors=LinearS)
```

Figure 25: Run codes

D:\Pyth\demo\plotcoherency

```
File Edit Search Source Run Debug Consoles Projects Tools View Help
D:\INGRIFIELD RAW DATA\demo\KL33A
19         (0.1, 0.0, 0.0),
20         (0.2, 0.0, 0.0),
21         (0.4, 0.0, 0.0),
22         (0.6, 1.0, 1.0),
23         (0.8, 1.0, 1.0),
24         (1.0, 0.0, 0.0),
25         ('blue'): ((0.0, 0.0, 0.0),
26             (0.2, 0.0, 0.0),
27             (0.4, 0.0, 0.0),
28             (0.6, 0.0, 0.0),
29             (0.8, 0.0, 0.0),
30             (1.0, 0.0, 0.0)),
31     my_cmap = matplotlib.colors.LinearSegmentedColormap
32
33     # 34
34     Z_all = bandavg.get('Zxy_single')
35     coh_selected_all = bandavg.get('coh_selectedEx')
36     coh_selected_ex = bandavg.get('cohMatrixEx')
37     coh_selected_ex = np.reshape(np.shape(bandavg.get('Ex'))[0], 7, 7)
38     Z_huber = Z_huber.get('7x7')
39     for fnum in range(np.size(ftlist)):
40         Z = Z_all[fnum,:]
41         coh_selected_ex = coh_selected_ex[fnum,:,:].reshape(7,7)
42         cc = coh_selected_ex[0,0]
43         cc = cc.reshape(-1,1)
44         Z = Z.reshape(-1,1)
45         ind_coh = np.where((coh_selected==0)[0].reshape(-1,1))
46         c = np.delete(cc, ind_coh).reshape(-1,1)
47         Z = np.delete(Z, ind_coh).reshape(-1,1)
48         Z[0] = 0
49         Z_imag = np.imag(Z)
50         plt.imshow(numznum)
51         plt.colorbar()
52         plt.title('KL33A - meas_2019-08-29_22-19-00 (1.0 Hz) f=0.05 Hz')
53         plt.savefig('C:/Users/Ajithabh/Desktop/myImagePDF.eps',
54             format='eps', dpi=1200)
```

Figure 26: Coherency values

As similar in the case of coherency threshold, run scripts in ‘plot-pd.py’ to plot polarization directions for each time window for all target frequencies (Figure 27). The top panel in the plot shows magnetic polarization directions and bottom panel shows electric polarization directions. Analysing the plots, we can identify the polarized segments. Polarization directions can be selected in two ways.

We can select a range of polarization direction to be discarded in the case 1. If we give ‘pdflag = 1’, ‘pdlim = [-10,10]’, and ‘alpha = alpha_degE’, all time windows with electric polarization direction values from -10 to 10 will be discarded. Use either magnetic polarization direction (‘alpha_degH’) or electric polarization direction (‘alpha_degE’) at a time (as in Figure 28). Keep ‘pdflag = 0’, when polarization direction based selection is not required.

Next is to mask time windows, give a range of time windows to be discarded in this case. In the example (Figure 28), the time windows between 0 and 40 ('timewindow_limits = [0,40]') will be discarded from processing.

‘mwflag’ should be 1 to perform the tasks.




Figure 27: Polarization directions

```
#====Data selection tools section. Coherency threshold & Polarization direction
# Calculation of coherency values for all time windows
AllcohEx = data_sel.cohtx(bandavg)
AllcohEy = data_sel.cohty(bandavg)
# Calculation of polarization directions for all time windows
alpha_degH,alpha_degE = data_sel.pdvalues(bandavg)
#
#===== Coherency threshold =====
ctflag = 0 # Give '1' to perform coherency threshold based selection
minpercent = 20 # Minimum percentage of windows required
CohThre = 0.9 # Coherency Threshold value Range: (0,1)
[cohMatrixEx, cohMatrixEy] = data_sel.performct(ctflag,CohThre,minpercent,ftlist,bandavg,AllcohEx,AllcohEy)
#
#===== Polarization direction =====
pdflag = 0 # Give '1' to perform polarization direction based selection
#>>> [10,10] #Polarization direction limit
alpha = alpha_degE # Use either alpha_degE (electric field) or alpha_degH (magnetic field)
pumat = data_sel.performpd(pdflag,pdlim,alpha,bandavg)

# This can be used to mask time windows based on the polarization directions
mwflag = 0 # Give '1' to perform mask windows
timewindow_limits = [0,40] #Time window limits
mwmat = data_sel.performmw(mwflag,timewindow_limits,bandavg)

#====End of data selection tools section
```

Figure 28: Magnetic or Electric Polarization direction

Once data selection constraints are set, just run a part of code as highlighted (to end of the script) in figure 29.

```

D:\Pyth\SigMT-Distribution - Spyder (Python 3.9)
File Edit Search Source Run Debug Consoles Projects Tools View Help
D:\Pyth\SigMT-Distribution\main_script.py
main_script.py
101 #===== Start band averaging =====
102 # No need to edit
103 # Average value after calibration and averaging using parzen window
104 ffile,bandavg = mproc.bandavg(tts,procinfo,config)
105
106 #===== Band averaging finished =====
107 timer_end = time.time()
108 print('Elapsed time: ' + str(timer_end - timer_start) +'s')
109 del timer_start, timer_end
110 print('Finished.')
111
112 #
113 #####Data selection tools section. Coherency threshold & Polarization direction
114 cohMatrixEx = np.ones(np.shape(bandavg.get('ExEx')),dtype=float)
115 cohMatrixEx *= np.ones(np.shape(bandavg.get('ExEx')),dtype=float)
116 cohMatrixEx *= np.ones(np.shape(bandavg.get('ExEx')),dtype=float)
117 # Calculation of coherency values for all time windows
118 AllcohEx = data_sel.cohEx(bandavg)
119 AllcohEy = data_sel.cohEy(bandavg)
120 # Calculation of polarization directions for all time windows
121 alpha_degM,alpha_degP = data_sel.pvalues(bandavg)
122
123 ##### Coherency threshold =====
124 ctflag = 0 # Give '1' to perform coherency threshold based selection
125 if ctflag == 1:
126     CohThre = [0.7,0.7,0.7,0.7,0.7,0.7,0.7,0.7,0.7,0.9,0.9,0.9]
127     for i in range(np.shape(AllcohEx)[0]):
128         for j in range(np.shape(AllcohEx)[1]):
129             if AllcohEx[i,j] < CohThre[i]:
130                 cohMatrixEx[i,j] = 0
131             else:
132                 cohMatrixEx[i,j] = 1
133
134

```

Figure 29: Run this part of script

5.4 Remote reference

The remote reference can be done similar as above example. But run ‘main_script_RR.py’ file. First you have to enter the site you need to process and enter the measurement number. Then enter the remote site name and measurement number.